

A

C Analytical & Consulting LLC

PO Box 248

Bemidji, MN 56619-0248

218-243-3328

State Certified Well Water Testing Laboratory: 027-007-346



**INFO WE NEED FROM YOU:** Collection: Date \_\_\_\_\_ Time \_\_\_\_\_ (AM) (PM)  
Owners Name \_\_\_\_\_ Collected By \_\_\_\_\_  
Sample Address \_\_\_\_\_  
Mailing Address \_\_\_\_\_  
Agent/Agency/Phone \_\_\_\_\_  
Collection Point (Well, Kitchen, Spigot) \_\_\_\_\_ Phone: \_\_\_\_\_

**TEST OPTIONS:**

_____ Nitrates, E-Coli and Total Coliform Bacteria	<b>\$45</b>
_____ Iron and Hardness	<b>\$15</b>
_____ Lead	<b>\$40</b>
_____ Arsenic	<b>\$40</b>
<b>TOTAL</b>	<b>\$ _____</b>

**MAKE PAYABLE TO:**  
**INSTRUCTIONS:**

**\*Each test requires a separate bottle**  
AC Analytical & Consulting LLC Check must be included.  
Must be followed carefully and prepaid or tests will not be run.

**Nitrates & Bacteria**

**DO NOT MAIL AT POST OFFICE, we have 30 hours from time of collection to testing and the Post Office is unable to achieve that. A list of SPEEDEE Delivery shipping locations is on the back of this form.**

-Samples need to be collected and shipped on the same day before last pickup (Monday-Thursday), **OR** collected and dropped off the same day at Beltrami Environmental Services / SWCD Office (701 Minnesota Ave NW, Ste 113 Bemidji MN) Monday-Friday before 9:30 am.

- Wash hands thoroughly with soap and water.
- Sample should be taken from an outlet that can be sterilized. Remove screen & plastic parts. Kitchen faucets with pullout sprayers do not work well for collection sites, try bathtub or utility sink instead.
- Briefly expose outlet to flame (small torch, lighter) or swab with rubbing alcohol to sterilize.
- Turn on **Cold** water and let run for 5 minutes to clear standing water from line.
- Open sterile bottle making sure not to contaminate with fingers or debris. **There are 2 lines on the bottle, fill bottle to the UPPER line, leaving a 1-inch air space.** Replace cover and snug so that it will not leak in transit.

**Iron and Hardness**

There is no need to sterilize outlet for this test. Samples need to be taken at point of interest. Collect sample before softeners or filters to check raw water. Collect sample after softeners or filters to check performance of the device. If you wish to do both, then two sample bottles are required. This test is not MDH Certified.

**Lead or Arsenic**

Obtain an instruction sheet for Lead or call the lab for instructions. Lead and Arsenic testing is contracted through Water Labs Inc. Elk River MN, which is a Minnesota Department of Health Certified Lab.

# A C Analytical & Consulting LLC

PO Box 248  
Bemidji, MN 56619-0248

218-243-3328

State Certified Well Water Testing Laboratory: 027-007-346



City	Drop Off	Address	Pick upTime
Baudette, MN-	Auto Value	808 MN-11	(Before 1 PM)
Grand Rapids, MN	Shippin Shack	2 3 <sup>rd</sup> Street NE, #6c	(Before 1 PM)
Park Rapids, MN-	Auto Value	801 1 <sup>st</sup> Street E	(Before 10 AM)
Roseau, MN-	Auto Value	121 2 <sup>nd</sup> Street W	(Before 12 PM)
	Lumberyard	505 5 <sup>th</sup> Ave NW	(Before 1 PM)
Walker, MN-	Qwik Pack & Ship,	507 Minnesota Ave. W.	(Before 1 PM)
	Thrifty White Drug	603 Minnesota Ave. W	(Before 1 PM)
Warroad, MN-	Thrifty White Drug	310 Lake St NE, #780	(Before 1 PM)
Thief River Falls, MN-	SPEE DEE WALKIN	1319 Greenwood St W	(7:30 AM-8:00 AM) OR (5:00 PM-6:00 PM)